

Ohm - Desktop Version

1.0

Generated by Doxygen 1.8.12

Contents

1	Module Index	1
1.1	Modules	1
2	Namespace Index	3
2.1	Packages	3
3	Hierarchical Index	5
3.1	Class Hierarchy	5
4	Class Index	7
4.1	Class List	7
5	Module Documentation	9
5.1	UserInterface	9
5.1.1	Detailed Description	9
5.2	ColourMapping	10
5.2.1	Detailed Description	10
5.3	ValueCalculator	11
5.3.1	Detailed Description	11
5.4	BandLocation	12
5.4.1	Detailed Description	12
5.5	CameraInput	13
5.5.1	Detailed Description	13
5.6	ImageInput	14
5.6.1	Detailed Description	14

6	Namespace Documentation	15
6.1	Package imageprocessing	15
6.1.1	Detailed Description	15
6.2	Package input	15
6.2.1	Detailed Description	15
6.3	Package UserInterface	15
6.3.1	Detailed Description	15
6.4	Package valueidentification	15
6.4.1	Detailed Description	15
7	Class Documentation	17
7.1	ohm.imageprocessing.BandReader Class Reference	17
7.1.1	Detailed Description	17
7.1.2	Member Function Documentation	17
7.1.2.1	abmag()	17
7.1.2.2	boxSample()	18
7.1.2.3	componentwiseMean()	18
7.1.2.4	diff()	19
7.1.2.5	dist()	19
7.1.2.6	findGlobalMaxima()	19
7.1.2.7	findLocalMaxima()	20
7.1.2.8	groupTerms()	20
7.1.2.9	mag()	20
7.1.2.10	onLine()	21
7.1.2.11	read()	21
7.1.2.12	rollingAverageFilter()	21
7.1.2.13	sample()	22
7.2	ohm.input.CameraInput Class Reference	22
7.2.1	Detailed Description	23
7.2.2	Member Function Documentation	23
7.2.2.1	getImage()	23

7.2.2.2	getLAB()	23
7.2.2.3	getRGB()	23
7.3	ohm.Helpers Class Reference	24
7.3.1	Detailed Description	24
7.4	ohm.input.ImageInput Class Reference	24
7.4.1	Detailed Description	24
7.4.2	Constructor & Destructor Documentation	24
7.4.2.1	ImageInput() [1/2]	24
7.4.2.2	ImageInput() [2/2]	24
7.4.3	Member Function Documentation	25
7.4.3.1	getImage()	25
7.4.3.2	getLAB()	25
7.4.3.3	getRGB()	25
7.5	ohm.input.Input Interface Reference	26
7.5.1	Detailed Description	26
7.5.2	Member Function Documentation	26
7.5.2.1	getImage()	26
7.5.2.2	getLAB()	26
7.5.2.3	getRGB()	27
7.6	ohm.userinterface.LiveImageView Class Reference	27
7.6.1	Detailed Description	27
7.7	ohm.Ohm Class Reference	28
7.8	ohm.userinterface.OhmViewController Class Reference	28
7.8.1	Detailed Description	28
7.8.2	Member Function Documentation	29
7.8.2.1	initialize()	29
7.9	ohm.userinterface.ResistorAxisPickerView Class Reference	29
7.9.1	Detailed Description	29
7.9.2	Member Function Documentation	29
7.9.2.1	setImage()	29

7.9.2.2	<code>setListener()</code>	30
7.10	<code>ohm.valueidentification.ResistorColour</code> Enum Reference	30
7.10.1	Detailed Description	31
7.10.2	Constructor & Destructor Documentation	31
7.10.2.1	<code>ResistorColour()</code>	31
7.10.3	Member Function Documentation	31
7.10.3.1	<code>[static initializer]()</code>	31
7.10.3.2	<code>fit()</code> [1/2]	31
7.10.3.3	<code>fit()</code> [2/2]	32
7.10.3.4	<code>rgb2lab()</code>	32
7.11	<code>ohm.valueidentification.ValueCalculator</code> Class Reference	32
7.11.1	Detailed Description	33
7.11.2	Constructor & Destructor Documentation	33
7.11.2.1	<code>ValueCalculator()</code>	33
7.11.3	Member Function Documentation	33
7.11.3.1	<code>getValue()</code>	33
Index		35

Chapter 1

Module Index

1.1 Modules

Here is a list of all modules:

UserInterface	9
ColourMapping	10
ValueCalculator	11
BandLocation	12
CameraInput	13
ImageInput	14

Chapter 2

Namespace Index

2.1 Packages

Here are the packages with brief descriptions (if available):

imageprocessing	15
input	15
UserInterface	15
valueidentification	15

Chapter 3

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

ohm.imageprocessing.BandReader	17
ohm.Helpers	24
ohm.input.Input	26
ohm.input.CameraInput	22
ohm.input.ImageInput	24
ohm.valueidentification.ResistorColour	30
ohm.valueidentification.ValueCalculator	32
Application	
ohm.Ohm	28
EventHandler	
ohm.userinterface.ResistorAxisPickerView	29
ImageView	
ohm.userinterface.LiveImageView	27
ohm.userinterface.ResistorAxisPickerView	29
Initializable	
ohm.userinterface.OhmViewController	28

Chapter 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

ohm.imageprocessing.BandReader	
Module used to analyze the line of pixels selected by the user through the UI. It uses high values of the differential of the RGB colours to detect edges of bands	17
ohm.input.CameraInput	
Class used to receive input from the camera on Desktop	22
ohm.Helpers	24
ohm.input.ImageInput	
A source of input data, uses static images	24
ohm.input.Input	26
ohm.userinterface.LiveImageView	
The LiveImageView is an ImageView that periodically calls a Renderer to produce a new image that the ImageView then displays. This is useful to create images from real time updating images/data	27
ohm.Ohm	28
ohm.userinterface.OhmViewController	
Coordinates the algorithms present in the model with user input through the view	28
ohm.userinterface.ResistorAxisPickerView	
This class displays an opencv Mat as an image and allows the user to pick two endpoints of a line. Once two valid points, a listener is called	29
ohm.valueidentification.ResistorColour	
Enum containing all of the possible colours that a resistor can take on. Also features member functions used to map the colours of bands to values used in the calculation process	30
ohm.valueidentification.ValueCalculator	
Object used to calculate the resistance of the resistor based on the mapped colours	32

Chapter 5

Module Documentation

5.1 `UserInterface`

Classes

- class [ohm.userinterface.LiveImageView](#)

The [LiveImageView](#) is an `ImageView` that periodically calls a `Renderer` to produce a new image that the `ImageView` then displays. This is useful to create images from real time updating images/data.

- class [ohm.userinterface.OhmViewController](#)

Coordinates the algorithms present in the model with user input through the view.

- class [ohm.userinterface.ResistorAxisPickerView](#)

This class displays an `opencv Mat` as an image and allows the user to pick two endpoints of a line. Once two valid points, a listener is called.

5.1.1 Detailed Description

5.2 ColourMapping

Classes

- enum [ohm.valueidentification.ResistorColour](#)

Enum containing all of the possible colours that a resistor can take on. Also features member functions used to map the colours of bands to values used in the calculation process.

5.2.1 Detailed Description

Author

Jonathan Brown

5.3 ValueCalculator

Classes

- class [ohm.valueidentification.ValueCalculator](#)

Object used to calculate the resistance of the resistor based on the mapped colours.

5.3.1 Detailed Description

Author

Jonathan Brown

5.4 BandLocation

Classes

- class [ohm.imageprocessing.BandReader](#)

Module used to analyze the line of pixels selected by the user through the UI. It uses high values of the differential of the RGB colours to detect edges of bands.

5.4.1 Detailed Description

Module used to analyze the line of pixels selected by the user through the UI. It uses high values of the differential of the RGB colours to detect edges of bands.

5.5 CameraInput

Classes

- class [ohm.input.CameraInput](#)

Class used to receive input from the camera on Desktop.

5.5.1 Detailed Description

Author

Graeme Crawley

5.6 ImageInput

Classes

- class [ohm.input.ImageInput](#)
A source of input data, uses static images.

5.6.1 Detailed Description

Chapter 6

Namespace Documentation

6.1 Package imageprocessing

6.1.1 Detailed Description

Contains the Band Location and Resistor Body Identification modules.

6.2 Package input

6.2.1 Detailed Description

This package contains the components of the Camera and ImageFile modules. They hide the applications access to the hardware (camera or file system).

6.3 Package UserInterface

6.3.1 Detailed Description

Contains the views and the controller of the application. This is a Behavioural Module who's secret is the UI components of the application.

6.4 Package valueidentification

6.4.1 Detailed Description

Contains the Colour Mapping and Value Identification Modules

Chapter 7

Class Documentation

7.1 ohm.imageprocessing.BandReader Class Reference

Module used to analyze the line of pixels selected by the user through the UI. It uses high values of the differential of the RGB colours to detect edges of bands.

Static Public Member Functions

- static List< Point > [read](#) (Mat frame, Point p1, Point p2)
- static double [][] [boxSample](#) (Mat mat, Point start, Point end, int nSamples, double boxWidth)
- static double [][] [rollingAverageFilter](#) (double[][] [sample](#), int windowRadius)
- static double [] [componentwiseMean](#) (double[][] samples)
- static double [][] [sample](#) (Mat mat, Point start, Point end, int nSamples)
- static double [][] [diff](#) (double[][] y)
- static double [abmag](#) (double[] vect)
- static double [mag](#) (double[] vect)
- static double [dist](#) (Point p1, Point p2)
- static double [] [groupTerms](#) (double[] terms, int binSize)
- static List< Pair< Integer, Double > > [findLocalMaxima](#) (double[] values)
- static List< Pair< Integer, Double > > [findGlobalMaxima](#) (double[] values, int nMaxima)
- static Point [onLine](#) (Point start, Point end, double fraction)

7.1.1 Detailed Description

Module used to analyze the line of pixels selected by the user through the UI. It uses high values of the differential of the RGB colours to detect edges of bands.

Author

Ryan Marks & Jonathan Brown

7.1.2 Member Function Documentation

7.1.2.1 [abmag\(\)](#)

```
static double ohm.imageprocessing.BandReader.abmag (  
    double [] vect ) [static]
```

Calculate the magnitude of a given vector

Parameters

<i>vect</i>	input vector
-------------	--------------

Returns

The magnitude of the input vector

7.1.2.2 boxSample()

```
static double [][] ohm.imageprocessing.BandReader.boxSample (
    Mat mat,
    Point start,
    Point end,
    int nSamples,
    double boxWidth ) [static]
```

This method takes something Ryan made up called a box sample. At nSamples points along the line from start to end, a line of samples are take along a line of length boxWidth, normal to and centred on the sampling line

Parameters

<i>mat</i>	The matrix being sampled
<i>start</i>	The start of the sampling line
<i>end</i>	The end of the sampling line
<i>nSamples</i>	The number or linear samples to take along the sampling line
<i>boxWidth</i>	the length of the normal sampling line.

Returns

An array containing the average rgb values (represented as double[]) in the sampling window.

7.1.2.3 componentwiseMean()

```
static double [] ohm.imageprocessing.BandReader.componentwiseMean (
    double samples[][] ) [static]
```

Calculate the mean of an array of vectors.

Parameters

<i>samples</i>	Array of RGB vectors represented as double[]
----------------	--

Returns

The average of all vectors within the input array (represented as a double[])

7.1.2.4 diff()

```
static double [][] ohm.imageprocessing.BandReader.diff (
    double y[][] ) [static]
```

Take the discrete derivative of a series of vectors.

Parameters

<i>y</i>	A series of vectors
----------	---------------------

Returns

y' , the derivative of the input represented as a array of vectors (double[][]).

7.1.2.5 dist()

```
static double ohm.imageprocessing.BandReader.dist (
    Point p1,
    Point p2 ) [static]
```

Calcualte the distance between two points.

Parameters

<i>p1</i>	Point 1.
<i>p2</i>	Point 2.

Returns

Distance between *p1* and *p2*.

7.1.2.6 findGlobalMaxima()

```
static List<Pair<Integer,Double> > ohm.imageprocessing.BandReader.findGlobalMaxima (
    double [] values,
    int nMaxima ) [static]
```

Get the *n* largest values in a sample/

Parameters

<i>values</i>	the input signal
<i>nMaxima</i>	The number of maxima to find

Returns

A list of (index, value) Pairs representing the global maxima in the sample

7.1.2.7 findLocalMaxima()

```
static List<Pair<Integer,Double> > ohm.imageprocessing.BandReader.findLocalMaxima (
    double [] values ) [static]
```

Find all the local maxima in an array of doubles

Parameters

<i>values</i>	the input signal
---------------	------------------

Returns

A list of (index, value) Pairs representing the local maxima

7.1.2.8 groupTerms()

```
static double [] ohm.imageprocessing.BandReader.groupTerms (
    double [] terms,
    int binSize ) [static]
```

Take a large array of samples and collect the samples into bins

Parameters

<i>terms</i>	The array of samples
<i>binSize</i>	The size of the bins

Returns

The binned samples

7.1.2.9 mag()

```
static double ohm.imageprocessing.BandReader.mag (
    double [] vect ) [static]
```

Calculate the magnitude of a given vector

Parameters

<i>vect</i>	input vector
-------------	--------------

Returns

The magnitude of the input vector

7.1.2.10 onLine()

```
static Point ohm.imageprocessing.BandReader.onLine (
    Point start,
    Point end,
    double fraction ) [static]
```

Get a point that is some fraction between two others.

Parameters

<i>start</i>	The starting point of the line
<i>end</i>	The endpoint of the line
<i>fraction</i>	The fraction of the way between start and end

Returns

A point that is fraction between start and end

7.1.2.11 read()

```
static List<Point> ohm.imageprocessing.BandReader.read (
    Mat frame,
    Point p1,
    Point p2 ) [static]
```

Parameters

<i>frame</i>	Image to Sample.
<i>p1</i>	Starting point of the sampling line.
<i>p2</i>	Ending point of the sampling line.

Returns

List of points along the line that are likely band edges.

7.1.2.12 rollingAverageFilter()

```
static double [][] ohm.imageprocessing.BandReader.rollingAverageFilter (
    double sample[][],
    int windowRadius ) [static]
```

This method is used to apply a rolling average filter to vector data.

Parameters

<i>sample</i>	An array of (arrays of doubles representing an individual vector sample)
<i>windowRadius</i>	The number of samples on either side of a given sample to incorporate into the average

Returns

An array containing the average RGB value sampled along the line.

7.1.2.13 sample()

```
static double [][] ohm.imageprocessing.BandReader.sample (
    Mat mat,
    Point start,
    Point end,
    int nSamples ) [static]
```

Take a linear sampling from a matrix at a given number of points along a line

Parameters

<i>mat</i>	The matrix to be sampled
<i>start</i>	The start of the sampling line
<i>end</i>	The end of the sampling line
<i>nSamples</i>	The number of samples to take along the line.

Returns

The samples taken


The documentation for this class was generated from the following file:

- `java/ohm/imageprocessing/BandReader.java`

7.2 ohm.input.CameraInput Class Reference

Class used to receive input from the camera on Desktop.

Inheritance diagram for ohm.input.CameraInput:

**Public Member Functions**

- Image `getImage ()`
- Mat `getRGB ()`
- Mat `getLAB ()`

7.2.1 Detailed Description

Class used to receive input from the camera on Desktop.

7.2.2 Member Function Documentation

7.2.2.1 getImage()

```
Image ohm.input.CameraInput.getImage ( )
```

Used to retrieve a image representation of the input (used by JavaFX).

Returns

Image representation of input.

Implements [ohm.input.Input](#).

7.2.2.2 getLAB()

```
Mat ohm.input.CameraInput.getLAB ( )
```

Used to retrieve a rgb matrix representation of the input (used by Opencv libraries).

Returns

Matrix representation of input.

Implements [ohm.input.Input](#).

7.2.2.3 getRGB()

```
Mat ohm.input.CameraInput.getRGB ( )
```

Used to retrieve a rgb matrix representation of the input (used by Opencv libraries).

Returns

Matrix representation of input.

Implements [ohm.input.Input](#).

The documentation for this class was generated from the following file:

- `java/ohm/input/CameraInput.java`

7.3 ohm.Helpers Class Reference

Static Public Member Functions

- static Image **matToImage** (Mat mat)

7.3.1 Detailed Description

Module featuring static methods used by multiple other modules in order to perform common computations. Will be eliminated in final release.


The documentation for this class was generated from the following file:

- java/ohm/Helpers.java

7.4 ohm.input.ImageInput Class Reference

A source of input data, uses static images.

Inheritance diagram for ohm.input.ImageInput:



Public Member Functions

- [ImageInput](#) ()
- [ImageInput](#) (String name)
- Mat [getRGB](#) ()
- Image [getImage](#) ()
- Mat [getLAB](#) ()

7.4.1 Detailed Description

A source of input data, uses static images.

Author

Jonathan Brown

7.4.2 Constructor & Destructor Documentation

7.4.2.1 ImageInput() [1/2]

```
ohm.input.ImageInput.ImageInput ( )
```

Default constructor creates an instance using a default image.

7.4.2.2 ImageInput() [2/2]

```
ohm.input.ImageInput.ImageInput (
    String name )
```

Constructor featuring a name parameter.

Parameters

<i>name</i>	The name of the input image. Do not include an extension.
-------------	---

7.4.3 Member Function Documentation

7.4.3.1 getImage()

```
Image ohm.input.ImageInput.getImage ( )
```

Used to retrieve a image representation of the input (used by JavaFX).

Returns

Image representation of input.

Implements [ohm.input.Input](#).

7.4.3.2 getLAB()

```
Mat ohm.input.ImageInput.getLAB ( )
```

Used to retrieve a rgb matrix representation of the input (used by Opencv libraries).

Returns

Matrix representation of input.

Implements [ohm.input.Input](#).

7.4.3.3 getRGB()

```
Mat ohm.input.ImageInput.getRGB ( )
```

Method returns a OpenCV Matrix of the loaded image.

Returns

OpenCV Matrix representation of the image.


Implements [ohm.input.Input](#).

The documentation for this class was generated from the following file:

- `java/ohm/input/ImageInput.java`

7.5 ohm.input.Input Interface Reference

Inheritance diagram for ohm.input.Input:



Public Member Functions

- Mat [getRGB](#) ()
- Image [getImage](#) ()
- Mat [getLAB](#) ()

7.5.1 Detailed Description

Author

Jonathan Brown

7.5.2 Member Function Documentation

7.5.2.1 [getImage\(\)](#)

Image `ohm.input.Input.getImage ()`

Used to retrieve a image representation of the input (used by JavaFX).

Returns

Image representation of input.

Implemented in [ohm.input.CameraInput](#), and [ohm.input.ImageInput](#).

7.5.2.2 [getLAB\(\)](#)

Mat `ohm.input.Input.getLAB ()`

Used to retrieve a rgb matrix representation of the input (used by Opencv libraries).

Returns

Matrix representation of input.

Implemented in [ohm.input.CameraInput](#), and [ohm.input.ImageInput](#).

7.5.2.3 getRGB()

```
Mat ohm.input.Input.getRGB ( )
```

Used to retrieve a rgb matrix representation of the input (used by OpenCV libraries).

Returns

Matrix representation of input.

Implemented in [ohm.input.CameraInput](#), and [ohm.input.ImageInput](#).


The documentation for this interface was generated from the following file:

- `java/ohm/input/Input.java`

7.6 ohm.userinterface.LiveImageView Class Reference

The [LiveImageView](#) is an [ImageView](#) that periodically calls a [Renderer](#) to produce a new image that the [ImageView](#) then displays. This is useful to create images from real time updating images/data.

Inheritance diagram for `ohm.userinterface.LiveImageView`:



Classes

- interface **Renderer**

Public Member Functions

- void **setFrameRate** (int frameRate)
- void **setRenderer** (Renderer newRenderer)

7.6.1 Detailed Description


The [LiveImageView](#) is an [ImageView](#) that periodically calls a [Renderer](#) to produce a new image that the [ImageView](#) then displays. This is useful to create images from real time updating images/data.

The documentation for this class was generated from the following file:

- `java/ohm/userinterface/LiveImageView.java`

7.7 ohm.Ohm Class Reference

Inheritance diagram for ohm.Ohm:



Public Member Functions

- void **start** (Stage primaryStage) throws Exception

Static Public Member Functions

- static void **main** (String[] args) throws Exception


The documentation for this class was generated from the following file:

- java/ohm/Ohm.java

7.8 ohm.userinterface.OhmViewController Class Reference

Coordinates the algorithms present in the model with user input through the view.

Inheritance diagram for ohm.userinterface.OhmViewController:



Public Member Functions

- void **initialize** (URL url, ResourceBundle rb)
- void **buttonClicked** (ActionEvent actionEvent)

Public Attributes

- Button **startCameraButton**

7.8.1 Detailed Description

Coordinates the algorithms present in the model with user input through the view.

7.8.2 Member Function Documentation

7.8.2.1 initialize()

```
void ohm.userinterface.OhmViewController.initialize (
    URL url,
    ResourceBundle rb )
```

Method used to "glue" together the front and back end of the application.


The documentation for this class was generated from the following file:

- java/ohm/userinterface/OhmViewController.java

7.9 ohm.userinterface.ResistorAxisPickerView Class Reference

This class displays an opencv Mat as an image and allows the user to pick two endpoints of a line. Once two valid points, a listener is called.

Inheritance diagram for ohm.userinterface.ResistorAxisPickerView:



Classes

- interface **Listener**

Public Member Functions

- void **handle** (MouseEvent event)
- void **setImage** (Mat newImage)
- void **setListener** (Listener listener)

Static Public Member Functions

- static double **dist** (Point p1, Point p2)

7.9.1 Detailed Description

This class displays an opencv Mat as an image and allows the user to pick two endpoints of a line. Once two valid points, a listener is called.

7.9.2 Member Function Documentation

7.9.2.1 setImage()

```
void ohm.userinterface.ResistorAxisPickerView.setImage (
    Mat newImage )
```

Set the matrix to display

Parameters

<i>newImage</i>	Image to be set as the image to be displayed in the UI
-----------------	--

7.9.2.2 `setListener()`

```
void ohm.userinterface.ResistorAxisPickerView.setListener (
    Listener listener )
```

Assign a line listener to be updated when new points are selected

Parameters

<i>listener</i>	Object that triggers responds to a mouse click inside the view.
-----------------	---

The documentation for this class was generated from the following file:

- `java/ohm/userinterface/ResistorAxisPickerView.java`

7.10 `ohm.valueidentification.ResistorColour` Enum Reference

Enum containing all of the possible colours that a resistor can take on. Also features member functions used to map the colours of bands to values used in the calculation process.

Public Member Functions

- [ResistorColour](#) (int v)

Static Public Member Functions

- [\[static initializer\]](#)
- static void [rgb2lab](#) (float R, float G, float B, float[] lab)
- static int [fit](#) (float r, float g, float b)
- static int [fit](#) (int r, int g, int b, int colorSpace)
- static int [fit](#) (double r, double g, double b, int colorSpace)

Public Attributes

- **BLACK** =(0)
- **BROWN** =(1)
- **RED** =(2)
- **ORANGE** =(3)
- **YELLOW** =(4)
- **GREEN** =(5)
- **BLUE** =(6)
- **VIOLET** =(7)
- **GREY** =(8)
- **WHITE** =(9)
- **GOLD** =(11)
- **BASE** =(10)
- int **value**

Static Public Attributes

- static KNearest **KNN**

7.10.1 Detailed Description

Enum containing all of the possible colours that a resistor can take on. Also features member functions used to map the colours of bands to values used in the calculation process.

7.10.2 Constructor & Destructor Documentation

7.10.2.1 ResistorColour()

```
ohm.valueidentification.ResistorColour.ResistorColour (
    int v )
```

Parameters

<i>v</i>	The number represented by the colour in the calculation of the resistor's ohmage.
----------	---

•

7.10.3 Member Function Documentation

7.10.3.1 [static initializer]()

```
ohm.valueidentification.ResistorColour.[static initializer] ( ) [static]
```

Creates and trains the KNN classifier. Based on the training set stored in train.csv.

7.10.3.2 fit() [1/2]

```
static int ohm.valueidentification.ResistorColour.fit (
    int r,
    int g,
    int b,
    int colorSpace ) [static]
```

Function takes in a sampled colour from the images and attempts to fitOld it to the closest known colour a resistor can possess.

Parameters

<i>r</i>	The red colour value of the colour to be fitOld.
<i>g</i>	The green colour value of the colour to be fitOld.
<i>b</i>	The blue colour value of the colour to be fitOld.

Returns

The known colour that best represents the sampled colour.

7.10.3.3 fit() [2/2]

```
static int ohm.valueidentification.ResistorColour.fit (
    double r,
    double g,
    double b,
    int colorSpace ) [static]
```

Function takes in a sampled colour from the images and attempts to fitOld it to the closest known colour a resistor can possess.

Parameters

<i>r</i>	The red colour value of the colour to be fitOld.
<i>g</i>	The green colour value of the colour to be fitOld.
<i>b</i>	The blue colour value of the colour to be fitOld.

Returns

The known colour that best represents the sampled colour.

7.10.3.4 rgb2lab()

```
static void ohm.valueidentification.ResistorColour.rgb2lab (
    float R,
    float G,
    float B,
    float [] lab ) [static]
```

Method to convert a pixel from RGB space to lab space. Credit to: <http://www.brucelindbloom.com>

Parameters

<i>R</i>	Red value from 0f to 255f
<i>G</i>	Green value from 0f to 255f
<i>B</i>	Blue value from 0f to 255f
<i>lab</i>	Size three float[] containing the lab representation of the pixel.

The documentation for this enum was generated from the following file:

- `java/ohm/valueidentification/ResistorColour.java`

7.11 ohm.valueidentification.ValueCalculator Class Reference

Object used to calculate the resistance of the resistor based on the mapped colours.

Public Member Functions

- [ValueCalculator](#) (Integer a, Integer b, Integer c, Integer d)
- String [getValue](#) ()

7.11.1 Detailed Description

Object used to calculate the resistance of the resistor based on the mapped colours.

Author

Jonathan Brown

7.11.2 Constructor & Destructor Documentation

7.11.2.1 ValueCalculator()

```
ohm.valueidentification.ValueCalculator.ValueCalculator (
    Integer a,
    Integer b,
    Integer c,
    Integer d )
```

Parameters

<i>a</i>	Leftmost band value
<i>b</i>	2nd leftmost band value
<i>c</i>	3rd leftmost band value
<i>d</i>	Rightmost band value

7.11.3 Member Function Documentation

7.11.3.1 getValue()

```
String ohm.valueidentification.ValueCalculator.getValue ( )
```

Method to obtain the ohmage of the resistor calculated by the [ValueCalculator](#).

Returns

The documentation for this class was generated from the following file:

- `java/ohm/valueidentification/ValueCalculator.java`

Index

- [static initializer]
 - ohm::valueidentification::ResistorColour, [31](#)
- abmag
 - ohm::imageprocessing::BandReader, [17](#)
- BandLocation, [12](#)
- boxSample
 - ohm::imageprocessing::BandReader, [18](#)
- CameraInput, [13](#)
- ColourMapping, [10](#)
- componentwiseMean
 - ohm::imageprocessing::BandReader, [18](#)
- diff
 - ohm::imageprocessing::BandReader, [18](#)
- dist
 - ohm::imageprocessing::BandReader, [19](#)
- findGlobalMaxima
 - ohm::imageprocessing::BandReader, [19](#)
- findLocalMaxima
 - ohm::imageprocessing::BandReader, [19](#)
- fit
 - ohm::valueidentification::ResistorColour, [31](#), [32](#)
- getImage
 - ohm::input::CameraInput, [23](#)
 - ohm::input::ImageInput, [25](#)
 - ohm::input::Input, [26](#)
- getLAB
 - ohm::input::CameraInput, [23](#)
 - ohm::input::ImageInput, [25](#)
 - ohm::input::Input, [26](#)
- getRGB
 - ohm::input::CameraInput, [23](#)
 - ohm::input::ImageInput, [25](#)
 - ohm::input::Input, [26](#)
- getValue
 - ohm::valueidentification::ValueCalculator, [33](#)
- groupTerms
 - ohm::imageprocessing::BandReader, [20](#)
- ImageInput, [14](#)
 - ohm::input::ImageInput, [24](#)
- imageprocessing, [15](#)
- initialize
 - ohm::userinterface::OhmViewController, [29](#)
- input, [15](#)
- mag
 - ohm::imageprocessing::BandReader, [20](#)
- ohm.Helpers, [24](#)
- ohm.imageprocessing.BandReader, [17](#)
- ohm.input.CameraInput, [22](#)
- ohm.input.ImageInput, [24](#)
- ohm.input.Input, [26](#)
- ohm.Ohm, [28](#)
- ohm.userinterface.LiveImageView, [27](#)
- ohm.userinterface.OhmViewController, [28](#)
- ohm.userinterface.ResistorAxisPickerView, [29](#)
- ohm.valueidentification.ResistorColour, [30](#)
- ohm.valueidentification.ValueCalculator, [32](#)
- ohm::imageprocessing::BandReader
 - abmag, [17](#)
 - boxSample, [18](#)
 - componentwiseMean, [18](#)
 - diff, [18](#)
 - dist, [19](#)
 - findGlobalMaxima, [19](#)
 - findLocalMaxima, [19](#)
 - groupTerms, [20](#)
 - mag, [20](#)
 - onLine, [20](#)
 - read, [21](#)
 - rollingAverageFilter, [21](#)
 - sample, [22](#)
- ohm::input::CameraInput
 - getImage, [23](#)
 - getLAB, [23](#)
 - getRGB, [23](#)
- ohm::input::ImageInput
 - getImage, [25](#)
 - getLAB, [25](#)
 - getRGB, [25](#)
 - ImageInput, [24](#)
- ohm::input::Input
 - getImage, [26](#)
 - getLAB, [26](#)
 - getRGB, [26](#)
- ohm::userinterface::OhmViewController
 - initialize, [29](#)
- ohm::userinterface::ResistorAxisPickerView
 - setImage, [29](#)
 - setListener, [30](#)
- ohm::valueidentification::ResistorColour
 - [static initializer], [31](#)
 - fit, [31](#), [32](#)
 - ResistorColour, [31](#)

- rgb2lab, [32](#)
- ohm::valueidentification::ValueCalculator
 - getValue, [33](#)
 - ValueCalculator, [33](#)
- onLine
 - ohm::imageprocessing::BandReader, [20](#)
- read
 - ohm::imageprocessing::BandReader, [21](#)
- ResistorColour
 - ohm::valueidentification::ResistorColour, [31](#)
- rgb2lab
 - ohm::valueidentification::ResistorColour, [32](#)
- rollingAverageFilter
 - ohm::imageprocessing::BandReader, [21](#)
- sample
 - ohm::imageprocessing::BandReader, [22](#)
- setImage
 - ohm::userinterface::ResistorAxisPickerView, [29](#)
- setListener
 - ohm::userinterface::ResistorAxisPickerView, [30](#)
- UserInterface, [9](#), [15](#)
- ValueCalculator, [11](#)
 - ohm::valueidentification::ValueCalculator, [33](#)
- valueidentification, [15](#)